


Neuendorf

Controlling for a Third Variable (i.e., Checking for Mediation):
Correlation, Semi-partial Correlation, and Partial Correlation

SECTION 1: Measures of Association with Two Independent Variables—Expressed via Ballantines



$$r^2_{Y1} = a + c$$

zero-order bivariate correlation²

$$r^2_{Y2} = b + c$$

zero-order bivariate correlation²

$$R^2_{Y \cdot 12} = a + b + c$$

multiple correlation²

$$sr^2_1 = r^2_{Y(1 \cdot 2)} = R^2_{Y \cdot 12} - r^2_{Y2} = a/1$$

first order semi-partial correlation²

$$sr^2_2 = r^2_{Y(2 \cdot 1)} = R^2_{Y \cdot 12} - r^2_{Y1} = b/1$$

first order semi-partial correlation²

$$pr^2_1 = r^2_{Y1 \cdot 2} = \frac{R^2_{Y \cdot 12} - r^2_{Y2}}{1 - r^2_{Y2}} = \frac{a}{a + e}$$

first order partial correlation²

$$pr^2_2 = r^2_{Y2 \cdot 1} = \frac{R^2_{Y \cdot 12} - r^2_{Y1}}{1 - r^2_{Y1}} = \frac{b}{b + e}$$

first order partial correlation²

SECTION 2: The Role of Residuals

The Pearson zero-order correlation is calculated between the two sets of raw scores (e.g., X1 & Y)

<p>r_{y1} Zero-order correlation</p>
--

Community QOL <u>X1</u>	Neighborhood QOL <u>Y</u>
9	9
9	8
9	8
5	7
7	8
9	9
10	5
9	7
9	8
8	10
7	6
8	10
7	7
8	7
9	9
etc.	etc.

$r_{y(1\cdot2)}$ or Sr

Semi-partial correlation
(or, Part correlation)

The semi-partial correlation is calculated between the raw scores on Y (Neighborhood QOL) and the residuals (what is “left over”) for X1 (Community QOL) when some variable X2 (e.g., Value the Family) is regressed on X1:

$$X1' = a_1 + b_1X2$$

Residual Community QOL $X1 - X1'$	Neighborhood QOL Y
1.17911	9
1.46289	9
3.16557	8
-2.82089	7
-.82089	8
1.17911	9
2.17911	5
2.88179	7
1.17911	8
.17911	10
-.82089	6
.17911	10
-.82089	7
.17911	7
1.17911	9
etc.	etc.

$r_{y1.2}$ or pr

Partial correlation

The partial correlation is calculated between the residuals for X1 (Community QOL) and the residuals for Y (Neighborhood QOL) when the variable X2 (Value the Family) is regressed on X1 and on Y:

$$X1' = a_1 + b_1X2$$

$$Y' = a_2 + b_2X2$$

Residual Community QOL $X1 - X1'$	Residual Neighborhood QOL $Y - Y'$
1.17911	1.03026
1.46289	.32073
3.16557	2.06357
-2.82089	-.96974
-.82089	.03026
1.17911	1.03026
2.17911	-2.96974
2.88179	.77310
1.17911	.03026
.17911	2.03026
-.82089	-1.96974
.17911	2.03026
-.82089	-.96974
.17911	-.96974
1.17911	1.03026
etc.	etc.




SECTION 3: Patterns of Association when Controlling for a Third Variable: Comparing Correlations (r 's) and Partial Correlations (pr 's)

1. Partial Redundancy

$$r^2_{Y1} > pr^2_{Y1.2}$$

$$(\text{but } pr^2_{Y1.2} \neq 0)$$

Model examples:



2. Full Redundancy




$$pr^2_{Y1.2} = 0$$

(& implies $r^2_{Y1} \neq 0$)

Full redundancy can be associated with either of two main types of relationships:


- A. Spurious relationship (a found correlation between X1 and Y is not “real”)

Model examples:



- B. Indirect effect (the relationship between X1 and Y occurs only through X2)

Model example:




3. Suppression

$$r^2_{Y1} < pr^2_{Y1.2}$$

Model example:




(small or 0 r_{12})



4. No Effect (control has no impact)

$$r^2_{Y1} = pr^2_{Y1.2}$$

Model examples:




The following pages revisit these four types, with Ballantine examples.

1. Partial Redundancy

		$\frac{r_{Y1}^2}{}$	$\frac{Pr_{Y1.2}^2}{}$
e.g.#1		.20	.125
e.g.#2		.40	.29
e.g.#3		.70	.50
e.g.#4		.15	.06
e.g.#5		.85	.50

2. Full Redundancy




$\frac{r_{Y1}^2}{.30}$	$\frac{pr_{Y1\cdot 2}^2}{.00}$
------------------------	--------------------------------

Notice that $pr_{Y2\cdot 1}^2$ is *not* 0.


X1 has no unique contribution to Y.

Any of the three models shown under Full Redundancy could produce these numbers—we don't know which is true from correlational findings alone.


3. Suppression



.80	.83
-----	-----




.10	.33
-----	-----



.20	.29
-----	-----

Notice that as the overlap between X1 and X2 in the Y area is larger, redundancy grows. As *unique* contributions of X1 and X2 grow larger (i.e., little or no overlap of X1 and X2 in the Y area), suppression is greater.

4. No Effect



$$\frac{r_{Y1}^2}{.40}$$

$$\frac{Pr_{Y1.2}^2}{.40}$$